

for sabvoton controller how to use bluetooth to program


1.Download Mobile APP for sabvoton controller

A.for Android download




B.for iPhone ,find (**MQCON**)APP in the app store download


2.Find Sabvoton Controller's USB port line and communication signal line




3. Disconnect signal line , Plug in Bluetooth




4. Open your mobile phone bluetooth first, then Open the controller's Mobile APP , appear interface , Click connect , appear controller's bluetooth model , then Click



5. After bluetooth connect, appear interface as below picture, find the small arrow Click, appear Parameters, then Click middle pattern for setting :




7. Make regan braking function work : let E-brake(A) open, save; drop down find Regan enable, Let it Open and Save !




6. Change parameter example for motor parameter :

Click motor parameter, appear number ,change the number ,click OK

then click save ,will be ok (every time do not forget to Save)



7. After program , Back to Home page,Click ,appear disconnect ,then click



8. Finally unplugged the controller 's bluetooth ,let communication signal line connect



9. Restart the display on the handlebar ,then bike will as newly parameter to work !